

# MAX Copy Part

Easily copy a Part ID and all related data

With the MAX Copy Part utility you can easily copy a Part ID and all related data: Part Notes, Manufacturer's Part Number, Part Master Extended Fields, Associates, Alternate Process, Bill of Materials, Bill of Material Extended Fields, Bill of Material Notes, Bill of Material MPN BOM, Part Sales, and Part Sales Extended Fields.

MAX Copy Part

Part ID From:  Part ID To:

Part Master:

Description 1:  Description 1:

Description 2:  Description 2:

Part Notes (Windows\_Notes, TYPE:PM, 6 Records)

Manufacturer's Part Number (Mfg\_Part\_Master)

Part Master Extended Fields (Part\_Master\_Ext)

Associate (Document\_Link\_Mst, TYPE:PRTNUM, 4 Records)

Alternate Process (Alternate\_Process)

Bill of Materials (Product\_Structur, 4 Records)

Bill of Materials Extended Fields (Product\_Structure\_Ext)

Bill of Materials Notes (Windows\_Notes, TYPE:BM)

Bill of Materials MPN BOM (Mfg\_Part\_String)

Part Sales (Part\_Sales, 1 Records)

Description 1:  Description 1:

Description 2:  Description 2:

Part Sales Extended Fields (Part\_Sales\_Ext)

Exact MAX Sample Company    MANAGER    14-3-2016

After entering a valid Part ID From the number of existing related Part data records are shown, the shown number of records will be copied. Each type of related data can be included or excluded on copying a Part. The include and exclude settings are locally stored and remembered. The Part Master and Part Sales descriptions can be changed before creating the new Part ID To.

The following fields are not copied on creating to the Part ID To:

- Month To Date (MTD) and Year To Date (YTD) counters of the Part Master and Sales Master are set to zero.
- On hand quantity is set to zero
- The following Part Master dates are set to the current date:
  - Date Released to Production
  - Exception Date
  - Cost Calculation Date
  - Maintenance Manager Purchase Date
- Traceability fields CreationDate and ModificationDate are filled with the current date and the CreatedBy and ModifiedBy are filled with the current MAX Users.

The MAX Rename Utility uses the MAX User Security. Access to the MAX Rename utility has to be setup in the Security Editor of the MAX System Manager. On starting the MAX Rename utility a valid user name and password has to be supplied. The MAX Rename Utility can also be incorporated in the Tools menu of the Bill of Material, in this case the MAX login can be skipped and the current MAX user will be used.

©Velthoven Consulting, 2018. All rights reserved.  
All trademarks mentioned herein belong to their respective owners.

For further information please contact:  
Velthoven Consulting  
Reseller for MAX in Europe  
The Netherlands  
Phone: +31 (0)737110949  
Email: [sales@velthovenconsulting.com](mailto:sales@velthovenconsulting.com)  
Web: [www.velthovenconsulting.com](http://www.velthovenconsulting.com)